
tornadis Documentation

Release 0.7.0

Fabien MARTY

November 15, 2015

1	Requirements	1
2	Installation	3
3	First try (coroutines)	5
4	Second try (callbacks)	7
5	Go further: Pipeline	9
6	Installation without pip	11
7	API	13
7.1	Client API	13
7.2	PubSubClient API	14
7.3	Pipeline API	16
7.4	Exceptions	17
7.5	Connection API	17
	Python Module Index	19

Requirements

- Python 2.7 or Python ≥ 3.2
- unix operating system (linux, osx...)
- a running redis server (≥ 2.0)

Installation

With `pip` (without `pip` see at then end of this document):

```
pip install tornadis
```

First try (coroutines)

```
1 # Let's import tornado and tornadis
2 import tornado
3 import tornadis
4
5
6 @tornado.gen.coroutine
7 def talk_to_redis():
8     # let's (re)connect (autoconnect mode), call the ping redis command
9     # and wait the reply without blocking the tornado ioloop
10    # Note: call() method on Client instance returns a Future object (and
11    # should be used as a coroutine).
12    result = yield client.call("PING")
13    if isinstance(result, tornadis.TornadisException):
14        # For specific reasons, tornadis nearly never raises any exception
15        # they are returned as result
16        print "got exception: %s" % result
17    else:
18        # result is already a python object (a string in this simple example)
19        print "Result: %s" % result
20
21
22 # Build a tornadis.Client object with some options as kwargs
23 # host: redis host to connect
24 # port: redis port to connect
25 # autoconnect=True: put the Client object in auto(re)connect mode
26 client = tornadis.Client(host="localhost", port=6379, autoconnect=True)
27
28 # Start a tornado IOloop, execute the coroutine and end the program
29 loop = tornado.ioloop.IOLoop.instance()
30 loop.run_sync(talk_to_redis)
```

Second try (callbacks)

```
1 # Let's import tornado and tornadis
2 import tornado
3 import tornadis
4
5
6 def ping_callback(result):
7     if not isinstance(result, tornadis.TornadisException):
8         # For specific reasons, tornadis nearly never raises any exception
9         # they are returned as result
10        print "got exception: %s" % result
11    else:
12        # result is already a python object (a string in this simple example)
13        print "Result: %s" % result
14
15
16 @tornado.gen.coroutine
17 def main():
18     # let's (re)connect (autoconnect mode), call the ping redis command
19     # and wait the reply without blocking the tornado ioloop
20     # Note: async_call() method on Client instance does not return anything
21     # but the callback will be called later with the result.
22     client.async_call("PING", callback=ping_callback)
23     yield tornado.gen.sleep(1)
24
25
26 # Build a tornadis.Client object with some options as kwargs
27 # host: redis host to connect
28 # port: redis port to connect
29 # autoconnect=True: put the Client object in auto(re)connect mode
30 client = tornadis.Client(host="localhost", port=6379, autoconnect=True)
31
32 # Start a tornado IOLoop, execute the coroutine and end the program
33 loop = tornado.ioloop.IOLoop.instance()
34 loop.run_sync(main)
```

Go further: Pipeline

```
1 # Let's import tornado and tornadis
2 import tornado
3 import tornadis
4
5
6 @tornado.gen.coroutine
7 def pipeline_coroutine():
8     # Let's make a pipeline object to stack commands inside
9     pipeline = tornadis.Pipeline()
10    pipeline.stack_call("SET", "foo", "bar")
11    pipeline.stack_call("GET", "foo")
12
13    # At this point, nothing is sent to redis
14
15    # let's (re)connect (autoconnect mode), send the pipeline of requests
16    # (atomic mode) and wait all replies without blocking the tornado ioloop.
17    results = yield client.call(pipeline)
18
19    if isinstance(results, tornadis.TornadisException):
20        # For specific reasons, tornadis nearly never raises any exception
21        # they are returned as results
22        print "got exception: %s" % results
23    else:
24        # The two replies are in the results array
25        print results
26        # >>> ['OK', 'bar']
27
28
29 # Build a tornadis.Client object with some options as kwargs
30 # host: redis host to connect
31 # port: redis port to connect
32 # autoconnect=True: put the Client object in auto(re)connect mode
33 client = tornadis.Client(host="localhost", port=6379, autoconnect=True)
34
35 # Start a tornado IOloop, execute the coroutine and end the program
36 loop = tornado.ioloop.IOLoop.instance()
37 loop.run_sync(pipeline_coroutine)
```

Installation without pip

- install `tornado >= 4.2`
- install python wrapper for hiredis
- install `six`
- download and uncompress a `tornadis` release
- run `python setup.py install` in the `tornadis` directory

7.1 Client API

class `tornadis.Client` (*autoconnect=True, password=None, **connection_kwargs*)

Bases: `object`

High level object to interact with redis.

Variables

- **autoconnect** (*boolean*) – True if the client is in autoconnect mode (and in autoreconnection mode) (default True).
- **password** (*string*) – the password to authenticate with.
- **connection_kwargs** (*dict*) – `Connection` object kwargs (note that `read_callback` and `close_callback` args are set automatically).

__init__ (*autoconnect=True, password=None, **connection_kwargs*)

Constructor.

Parameters

- **autoconnect** (*boolean*) – True if the client is in autoconnect mode (and in autoreconnection mode) (default True).
- **password** (*string*) – the password to authenticate with.
- ****connection_kwargs** – `Connection` object kwargs.

async_call (**args, **kwargs*)

Calls a redis command, waits for the reply and call a callback.

Following options are available (not part of the redis command itself):

- **callback** Function called (with the result as argument) when the result is available. If not set, the reply is silently discarded. In case of errors, the callback is called with a `TornadisException` object as argument.

Parameters

- ***args** – full redis command as variable length argument list or a `Pipeline` object (as a single argument).
- ****kwargs** – options as keyword parameters.

Examples

```
>>> def cb(result):
    pass
>>> client.async_call("HSET", "key", "field", "val", callback=cb)
```

call (*args, **kwargs)

Calls a redis command and returns a Future of the reply.

Parameters

- ***args** – full redis command as variable length argument list or a Pipeline object (as a single argument).
- ****kwargs** – internal private options (do not use).

Returns a Future with the decoded redis reply as result (when available) or a ConnectionError object in case of connection error.

Raises *ClientError* – your Pipeline object is empty.

Examples

```
>>> @tornado.gen.coroutine
    def foobar():
        client = Client()
        result = yield client.call("HSET", "key", "field", "val")
```

connect (*args, **kwargs)

Connects the client object to redis.

It's safe to use this method even if you are already connected. Note: this method is useless with autoconnect mode (default).

Returns a Future object with True as result if the connection was ok.

disconnect ()

Disconnects the client object from redis.

It's safe to use this method even if you are already disconnected.

is_connected ()

Returns True if the client is connected to redis.

Returns True if the client is connected to redis.

7.2 PubSubClient API

class `tornadis.PubSubClient` (*autoconnect=True, password=None, **connection_kwargs*)

Bases: `tornadis.client.Client`

High level specific object to interact with pubsub redis.

The call() method is forbidden with this object.

More informations on the redis side: <http://redis.io/topics/pubsub>

__init__ (*autoconnect=True, password=None, **connection_kwargs*)

Constructor.

Parameters

- **autoconnect** (*boolean*) – True if the client is in autoconnect mode (and in autoreconnection mode) (default True).
- **password** (*string*) – the password to authenticate with.
- ****connection_kwargs** – *Connection* object kwargs.

async_call (**args, **kwargs*)

Not allowed method with PubSubClient object.

call (**args, **kwargs*)

Not allowed method with PubSubClient object.

connect (**args, **kwargs*)

Connects the client object to redis.

It's safe to use this method even if you are already connected. Note: this method is useless with autoconnect mode (default).

Returns a Future object with True as result if the connection was ok.

disconnect ()

Disconnects the client object from redis.

It's safe to use this method even if you are already disconnected.

is_connected ()

Returns True is the client is connected to redis.

Returns True if the client if connected to redis.

pubsub_pop_message (**args, **kwargs*)

Pops a message for a subscribed client.

Parameters **deadline** (*int*) – max number of seconds to wait (None => no timeout)

Returns Future with the popped message as result (or None if timeout or ConnectionError object in case of connection errors or ClientError object if you are not subscribed)

pubsub_psubscribe (**args*)

Subscribes to a list of patterns.

<http://redis.io/topics/pubsub>

Parameters ***args** – variable list of patterns to subscribe.

Returns Future with True as result if the subscribe is ok.

Return type Future

Examples

```
>>> yield client.pubsub_psubscribe("channel*", "foo*")
```

pubsub_punsubscribe (**args*)

Unsubscribes from a list of patterns.

<http://redis.io/topics/pubsub>

Parameters ***args** – variable list of patterns to unsubscribe.

Returns Future with True as result if the unsubscribe is ok.

Return type Future

Examples

```
>>> yield client.pubsub_punsubscribe("channel*", "foo*")
```

pubsub_subscribe (*args)

Subscribes to a list of channels.

<http://redis.io/topics/pubsub>

Parameters *args – variable list of channels to subscribe.

Returns Future with True as result if the subscribe is ok.

Return type Future

Examples

```
>>> yield client.pubsub_subscribe("channel1", "channel2")
```

pubsub_unsubscribe (*args)

Unsubscribes from a list of channels.

<http://redis.io/topics/pubsub>

Parameters *args – variable list of channels to unsubscribe.

Returns Future with True as result if the unsubscribe is ok.

Return type Future

Examples

```
>>> yield client.pubsub_unsubscribe("channel1", "channel2")
```

7.3 Pipeline API

class `tornadis.Pipeline`

Bases: `object`

Pipeline class to stack redis commands.

A pipeline object is just a kind of stack. You stack complete redis commands (with their corresponding arguments) inside it.

Then, you use the `call()` method of a `Client` object to process the pipeline (which must be the only argument of this `call()` call).

More informations on the redis side: <http://redis.io/topics/pipelining>

Variables

- **pipelined_args** – A list of tuples, each tuple is a complete redis command.
- **number_of_stacked_calls** – the number of stacked redis commands (integer).

`__init__()`
 Constructor.

`stack_call(*args)`
 Stacks a redis command inside the object.

The syntax is the same than the call() method a Client class.

Parameters `*args` – full redis command as variable length argument list.

Examples

```
>>> pipeline = Pipeline()
>>> pipeline.stack_call("HSET", "key", "field", "value")
>>> pipeline.stack_call("PING")
>>> pipeline.stack_call("INCR", "key2")
```

7.4 Exceptions

class `tornadis.TornadisException`

Bases: `exceptions.Exception`

Base Exception class.

class `tornadis.ConnectionError`

Bases: `tornadis.exceptions.TornadisException`

Exception raised when there is a connection error.

class `tornadis.ClientError`

Bases: `tornadis.exceptions.TornadisException`

Exception raised when there is a client error.

7.5 Connection API

Warning: this class is not public, it appears here just to document some kwargs. Do not use directly.

class `tornadis.Connection` (`read_callback`, `close_callback`, `host='127.0.0.1'`, `port=6379`,
`unix_domain_socket=None`, `read_page_size=65536`,
`write_page_size=65536`, `connect_timeout=20`, `tcp_nodelay=False`,
`aggressive_write=False`, `ioloop=None`)

Low level connection object.

Variables

- **host** (*string*) – the host name to connect to.
- **port** (*int*) – the port to connect to.
- **unix_domain_socket** (*string*) – path to a unix socket to connect to (if set, overrides host/port parameters).
- **read_page_size** (*int*) – page size for reading.
- **write_page_size** (*int*) – page size for writing.
- **connect_timeout** (*int*) – timeout (in seconds) for connecting.

- **tcp_nodelay** (*boolean*) – set TCP_NODELAY on socket.
- **aggressive_write** (*boolean*) – try to minimize write latency over global throughput (default False).

`__init__(read_callback, close_callback, host='127.0.0.1', port=6379, unix_domain_socket=None, read_page_size=65536, write_page_size=65536, connect_timeout=20, tcp_nodelay=False, aggressive_write=False, ioloop=None)`
Constructor.

Parameters

- **read_callback** – callback called when there is something to read (private, do not use from Client constructor).
- **close_callback** – callback called when the connection is closed (private, do not use from Client constructor).
- **host** (*string*) – the host name to connect to.
- **port** (*int*) – the port to connect to.
- **unix_domain_socket** (*string*) – path to a unix socket to connect to (if set, overrides host/port parameters).
- **read_page_size** (*int*) – page size for reading.
- **write_page_size** (*int*) – page size for writing.
- **connect_timeout** (*int*) – timeout (in seconds) for connecting.
- **tcp_nodelay** (*boolean*) – set TCP_NODELAY on socket.
- **aggressive_write** (*boolean*) – try to minimize write latency over global throughput (default False).
- **ioloop** (*IOLoop*) – the tornado ioloop to use.

t

tornadis, 14

Symbols

`__init__()` (tornadis.Client method), 13
`__init__()` (tornadis.Connection method), 18
`__init__()` (tornadis.Pipeline method), 16
`__init__()` (tornadis.PubSubClient method), 14

A

`async_call()` (tornadis.Client method), 13
`async_call()` (tornadis.PubSubClient method), 15

C

`call()` (tornadis.Client method), 14
`call()` (tornadis.PubSubClient method), 15
Client (class in tornadis), 13
ClientError (class in tornadis), 17
`connect()` (tornadis.Client method), 14
`connect()` (tornadis.PubSubClient method), 15
Connection (class in tornadis), 17
ConnectionError (class in tornadis), 17

D

`disconnect()` (tornadis.Client method), 14
`disconnect()` (tornadis.PubSubClient method), 15

I

`is_connected()` (tornadis.Client method), 14
`is_connected()` (tornadis.PubSubClient method), 15

P

Pipeline (class in tornadis), 16
`pubsub_pop_message()` (tornadis.PubSubClient method),
15
`pubsub_punsubscribe()` (tornadis.PubSubClient method), 15
`pubsub_punsubscribe()` (tornadis.PubSubClient method),
15
`pubsub_subscribe()` (tornadis.PubSubClient method), 16
`pubsub_unsubscribe()` (tornadis.PubSubClient method),
16
PubSubClient (class in tornadis), 14

S

`stack_call()` (tornadis.Pipeline method), 17

T

tornadis (module), 13, 14, 16, 17
TornadisException (class in tornadis), 17